

Erphpdown 插件使用教程

温馨提示：插件一般情况不支持 Windows 系统环境的虚拟主机，因为 Windows 系统的虚拟主机 PHP.ini 文件的默认设置没有开启 `extension=php_openssl.dll`，虚拟主机一般没法自己去修改 `php.ini`，所以只能联系虚拟主机提供商帮忙，打开 `php.ini`，找到 `;extension=php_openssl.dll`，将前面的“;”去掉；保存后重启环境即可。

压缩包介绍：

`erphpdown.zip` （主插件，必须安装）

`erphpdown-add-on-mycred.zip` （积分兑换插件，一般不推荐安装，给喜欢的朋友研究，但是如果安装了这个插件就必须也安装上 `mycred` 插件，不让前端会报错）

`erphpdown-add-on-card-2.0.zip` （批量生成充值卡插件，可选安装）

当你没有支付宝，微信等接口的时候，可以使用充值卡插件后台批量生成充值卡然后托管到第三方发卡平台，提供给用户购买。

`erphpdown V9 前端文件.zip` （插件自带的前端文件，可选安装）

插件安装方法：

WordPress 后台-插件-安装插件-上传插件-选择文件（选择插件压缩包上传）现在安装-启动插件

前端使用方法：

集成前端需要 WordPress 支持伪静态，在 WordPress 设置-固定连接，除了第一个选项，随便选择一个，然后去网站前台如果文章和分类能打开说明支持伪静态；

前端安装方法:

erphpdown V9 前端文件.zip 打开压缩包将压缩包内的 page-erphpdown-user.php 文件上传到你**当前使用主题**的根目录 (/wp-content/themes/你使用的主题名字文件夹), 然后去 WordPress 后台-页面-新建页面, 标题输入用户中心, 然后看网站右侧的页面属性-模板选择 erphpdown 个人中心, 然后看标题下面, 有个编辑可以编辑连接, 输入 user (为了页面链接美观) 然后发布这个页面即可。

简码前端:

一般情况用于集成前端不适合, 不兼容你主题的时候使用。

```
[ice_purchased_goods] //已购商品
[ice_purchased_tuiguang] //我的推广
[ice_purchased_tuiguangxiazai] //推广下载
[ice_purchased_tuiguangvip] //推广 vip
[ice_order_tracking] //订单查询
[ice_my_property] //我的资产
[ice_recharge_money] //充值
[ice_cash_application] //取现申请
[ice_cash_application_lists] //取现列表
[vip_tracking_lists] //VIP 订单查询
[ice_vip_member_service] //VIP 会员服务
[ice_zhuanzhang] //转账
```

比如我们使用[ice_my_property] //我的资产, 到 WordPress 后台-页面-新建页面, 标题输入我的资产, 然后复制 [ice_my_property] 到编辑器, 发布这个页面就OK。

PS: 一个页面可以放很多个简码。